Anchor

Boho style table runner

Anchor

🐼 🏶 🕺 🕷

AnchorCrafts.com

Designed by Sara Tschumi Design No.: 0022422-00001-05

MEZ Needlecraft GmbH, 2022. All Rights Reserved.



Anchor Crafty Fine 250g - Art. N° 4774200 - * (Colour n°)

1111 80 x 30 cm

2x *00105



Extras: 1 Chariot

Boho Style table runner

KNOTS USED:


Lark's head knot Square knot Diagonal double half hitch knot (see at the end step by step tutorials for these knots)

BEFORE STARTING


Cut the following: 20x 4200 cm ropes colour 00105

STEP BY STEP:


STEP 1: Fold all the ropes in half and with the help of a hanger make Lark's head knots one by one till you have 20.




STEP 2: On the first row make 10 square knots. On the second row make 9 more square knots starting from the 3rd rope counting left to right. Repeat process with 10 more squares knot on the 3rd row.



STEP 3: On the 4th row use 1st rope as a diagonal guideline and make 3 double half hitch knots with the 2nd, 3rd and 4th ropes respectively. Do the same from right to left using the 8th cord as guide and make knots with 7th, 6th and 5th ropes. Join the two halves making another loop on the guideline. Repeat this step, four more times to the right till you have in total 5 inverted triangles.



STEP 4: Use the diagonal double half hitch knot to make the rest of the "X" shape. Grab the 5th rope as a diagonal guideline and make 3 double half hitch knots. To complete the "X" shape use the 4th rope as a guideline to the opposite side and make 3 double half hitch knots with the 3rd, 2nd and 1st ropes. Repeat this 4 more times till you have 5 "X" shapes. In the end put all the knots together.






STEP 5: Repeat Step 2.




STEP 6: Leave an empty space of 10 cm down and repeat again Step 2. Do this 2 times more.



STEP 7: Repeat Step 3 -4.



STEP 8: Remove work from the holder cutting ends between the double knots, one by one until it is all loose. Measure 10 cm of fringes and cut the excess on both ends of the work. Unravel the yarn to give it more volume.




MACRAMÉ KNOTS TUTORIALS STEP BY STEP

LARK'S HEAD KNOT

Step 1: Fold one strand (consisting of a filler strand and a working strand) in half and place the loop on top of a cord, a rod or a ring.Step 2: Fold the loop down the back

Step 3: Pull the ends of the strand through the loop and pull tightly.



SQUARE KNOT – SQUARE KNOT BAND

Step 1: The 4 filler and working strands are arranged parallel, the working strands A and D are on the outside and the filler strands B/C are in the middle.

Step 2: Place D from right to left over B/C and under A.

Step 3: Bring A from left to right under B/C.

Step 4: Pull A from the back to the front though the loop created by D.

Step 5: Carefully pull A and D tightly.

The first basic knot is finished = 1 half square knot.


Step 6: Place D from left to right over B/C and under A

Step 7: Bring A from right to left under B/C. Pull A from the back to the front though the loop created by D.

Carefully pull A and D tightly.


0022422-00001-05

The second basic knot is finished = 1 square knot.



ABCD

Step 1



DIAGONAL DOUBLE HALF HITCH

From top left to bottom right / top right


Step 1: Take the first cord on the left (black) as the filler cord and the second cord (red) as the working cord. Place the filler cord over the working cord diagonally to the right. Loop the working cord around the filler cord. Step 2: Loop the working cord around the filler cord again.

Step 3: Gently pull the working cord tightly and push both loops together. Step 4: Use the next cord as the working cord and tie the next knot. Arrange this knot slightly lower/higher to create a diagonal line.

From top right to bottom left / top left

Step 1: Take the first cord to the right as the filler cord and the second cord as the working cord. Place the filler cord over the working cord diagonally to the left.

Step 2: Tie the knot as described above, but work in the opposite direction



Step 4

Note: Due to the fact, that Crafty Fine yarn is recycled from colour-assorted textile material and not re-dyed there can be slight variations in color and thickness. We therefore recommend buying enough yarn for your project. We also advise to use a crochet needle without handle, which is easier to work with. The first stitches might be a little bit hard to work, but you will soon get used, and the final result is worth it.

WASHING ADVICE

Always wash in as warm a water temperature as possible - up to the temperature recommended, with a short spin. Use a lot of water if hand washing. For darker colours we recommend the use of discolouration sheets. Do not bleach.

Do not tumble dry. Drip-dry on a horizontal surface. Iron on a hot temperature setting using a damp cloth. Professional dry cleaning in tetrachloroethylene.

Patterns & Content Copyright © Anchor (MEZ Needlecraft GmbH)

All rights reserved. No part of this publication may be reproduced, stored in a retrieval system or transmitted in any form or by any means, electronic, mechanical, photocopying, recording or otherwise, without the permission of the copyright owner. Designs may

not be made for resale. Extracts and image use must be approved with written permission from the copyright owner.

MEZ Needlecraft GmbH · Hauptstraße 78 · D-79336 Herbolzheim, Germany · AnchorCrafts.com